

INTRODUCTION TO Acoustics Module



Introduction to the Acoustics Module

© 1998-2018 COMSOL

Protected by patents listed on www.comsol.com/patents, and U.S. Patents 7,519,518; 7,596,474; 7,623,991; 8,457,932; 8,954,302; 9,098,106; 9,146,652; 9,323,503; 9,372,673; and 9,454,625. Patents pending.

This Documentation and the Programs described herein are furnished under the COMSOL Software License Agreement (www.comsol.com/comsol-license-agreement) and may be used or copied only under the terms of the license agreement.

COMSOL, the COMSOL logo, COMSOL Multiphysics, COMSOL Desktop, COMSOL Server, and LiveLink are either registered trademarks or trademarks of COMSOL AB. All other trademarks are the property of their respective owners, and COMSOL AB and its subsidiaries and products are not affiliated with, endorsed by, sponsored by, or supported by those trademark owners. For a list of such trademark owners, see www.comsol.com/trademarks.

Version: COMSOL 5.4

Contact Information

Visit the Contact COMSOL page at www.comsol.com/contact to submit general inquiries, contact Technical Support, or search for an address and phone number. You can also visit the Worldwide Sales Offices page at www.comsol.com/contact/offices for address and contact information.

If you need to contact Support, an online request form is located at the COMSOL Access page at www.comsol.com/support/case. Other useful links include:

- Support Center: www.comsol.com/support
- Product Download: www.comsol.com/product-download
- Product Updates: www.comsol.com/support/updates
- COMSOL Blog: www.comsol.com/blogs
- Discussion Forum: www.comsol.com/community
- Events: www.comsol.com/events
- COMSOL Video Gallery: www.comsol.com/video
- Support Knowledge Base: www.comsol.com/support/knowledgebase

Part number: CM020204

Contents

Introduction5
The Acoustics Module Physics Interfaces
Physics Interface Guide by Space Dimension and Study Type 14
The Application Libraries Window
Basics of Acoustics20
Governing Equations
Numerical Methods
Length and Time Scales
Boundary Conditions
Elastic Waves
Models with Losses
Geometrical Acoustics
Example: Absorptive Muffler
Model Definition
Domain Equations
Boundary Conditions
Results and Discussion
References31
Additional Examples from the Application Libraries 60
Eigenmodes in a Muffler60
Piezoacoustic Transducer60
Loudspeaker Driver in a Vented Enclosure
The Brüel & Kjær 4134 Condenser Microphone

Introduction

The Acoustics Module consists of a set of physics interfaces, which enable you to simulate the propagation of sound in fluids and solids in a fully multiphysics enabled environment. The available physics interfaces include pressure acoustics, acoustic-solid interaction, aeroacoustics (detailed convected acoustic models), thermoviscous acoustics, ultrasound, and geometrical acoustics. For acoustic analysis, covering many decades in the frequency spectrum as well as many formulations of the underlying equations, the Acoustics Module incorporates four numerical methods including finite elements (FEM), boundary elements (BEM), discontinuous Galerkin (dG-FEM), and ray tracing.




Figure 1: COMSOL model of the sound pressure level distribution in a muffler system.

Acoustic simulations using this module can easily solve classical problems such as scattering, diffraction, emission, radiation, and transmission of sound. These problems are relevant to muffler design, loudspeaker construction, sound insulation for absorbers and diffusers, the evaluation of directional acoustic patterns like directivity, noise radiation problems, and much more. The acoustic-structure multiphysics couplings enable modeling problems involving structure- and fluid-borne sound and their interaction. For example, acoustic-structure interaction is simulated for detailed muffler design, ultrasound piezo-actuators, sonar technology, and noise and vibration analysis of machinery in the automotive industry. Using the capabilities of COMSOL Multiphysics it is

also possible to analyze and design electroacoustic transducers such as loudspeakers, sensors, microphones, and hearing aid receivers.

Aeroacoustic problems can be analyzed and modeled by solving the linearized potential flow equations, the linearized Euler equations, or the linearized Navier-Stokes equations. These equations are used to model the one-way interaction between an external flow and an acoustic field, so-called convected acoustics. Applications range from jet-engine noise analysis to simulating acoustic flow sensors, liner systems with bias and/or gracing flow, and mufflers with flow.

The Thermoviscous Acoustics interfaces can accurately model systems having small geometrical dimensions where thermal and viscous boundary layer losses are important. This is relevant to the mobile phone and hearing aid industries, and for all transducer designers.

The Ultrasound branch includes the Convected Wave Equation, Time Explicit interface used to compute the transient propagation of linear ultrasound acoustic waves over large distances (relative to the wavelengths). The interface under the ultrasound branch is not restricted to high-frequency propagation, but can, in general, be applied to any acoustically large problem.




Figure 2: COMSOL model of an ultrasound flow meter modeled using the Convected Wave Equation interface. Model includes interaction with a steady state background flow.

Geometrical Acoustics includes the Ray Acoustics and the Acoustic Diffusion Equation interfaces. The physics are valid in the high-frequency limit where the acoustic wavelength is much smaller than the characteristic geometric features. Both interfaces are suited for modeling acoustics in rooms and concert halls. The Ray Acoustics interface can also be used, for example, in outdoor scenarios.

The Acoustics Module is of great benefit for engineers. By using 3D simulations, existing products can be optimized and new products more quickly designed with

virtual prototypes. Simulations also help designers, researchers, and engineers to gain insight into problems that are difficult to handle experimentally. Also, by optimizing a design virtually before real-life testing and manufacturing it, companies save time and money.




Figure 3: The Acoustics Module physics interfaces. Some physics interfaces require additional modules—both of the Acoustic-Shell Interaction interfaces and the Thermoviscous Acoustic-Shell Interaction interface require the Structural Mechanics Module. The Pipe Acoustics interfaces require the Pipe Flow Module.

The physics interfaces available with this module are shown in Figure 3 and are located under the Acoustics branch in the Model Wizard. The next section The Acoustics Module Physics Interfaces provides an overview of the physics interface functionality.

There are many application areas where these physics interfaces are used—from modeling simple pressure waves in air to examining complex interactions between elastic waves and pressure waves in porous materials. For a brief introduction to the basic concepts and theory of acoustics see the Basics of Acoustics.

The Acoustics Module application library has many examples of applications ranging from modeling sound insulation lining, loudspeakers and microphones, to mufflers. These examples show, among other things, how to simulate acoustic losses. The loss models range from homogenized empirical fluid models for fibrous materials to those that include thermal and viscous losses in detail using the Thermoviscous Acoustics interface.

The Linearized Potential Flow interface models the influence a mean background flow has on the sound field in, for example, a jet engine. Predefined couplings can be used to model the interaction between acoustic, structural, and electric fields in piezoelectric materials (see The Application Libraries Window for information about accessing these files). You can also get started with your own COMSOL modeling by going to the tutorial Example: Absorptive Muffler.

The Acoustics Module Physics Interfaces

There are six main branches—Pressure Acoustics, Acoustic-Structure Interaction, Aeroacoustics, Thermoviscous Acoustics, Ultrasound, and Geometrical Acoustics—and each of the physics interfaces are briefly described here, followed by the Physics Interface Guide by Space Dimension and Study Type listing the physics interface availability by space dimension and preset study types.

Pressure Acoustics

The Pressure Acoustics branch (\bigcirc) has interfaces where the sound field is described the pressure p. The physics interface solves acoustic problems in the frequency domain using the Pressure Acoustics, Frequency Domain interface (\bigcirc), where the Helmholtz equation is solved. Transient systems are modeled using the Pressure Acoustics, Transient interface (\bigcirc), where the classical wave equation is solved. Nonlinear effects can be included here using the Nonlinear Acoustics (Westervelt) feature. The Boundary Mode Acoustics interface (\bigcirc) is used to study propagating modes in waveguides and ducts (at a given frequency only a finite set of wave shapes can propagate over a long distance). To efficiently solve large radiation and scattering problems the Pressure Acoustics, Boundary Element interface (\bigcirc) solves the Helmholtz equation using the boundary

element method (BEM). The interface is fully multiphysics enabled and couples seamlessly with the finite element based interfaces, both acoustic and structural. The Pressure Acoustics, Time Explicit () interface uses a time explicit method based on discontinuous Galerkin finite elements to efficiently solve large transient problems.

A large variety of boundary conditions are available, including sound hard walls and conditions for applying sources. There are radiation, symmetry, and periodic conditions for modeling open boundaries. Impedance conditions include models for different parts of the human ear, human skin, simple RCL circuit models, and more. The physics interfaces also have several fluid models, which, in a homogenized way, mimic the behavior of sound propagation in more complex media. This includes the propagation in porous or fibrous materials (the Poroacoustics domain feature), the propagation in narrow structures of constant cross section (the Narrow Region Acoustics domain feature), and fluid models for defining bulk absorption behavior. Monopole, dipole, and quadrupole point sources can also be applied. So-called perfectly matched layers (PMLs) are also available to truncate an unbounded computational domain in both time and frequency domain. Finally, the far-field feature can be used to determine the pressure in any point outside the computational domain. Dedicated results and analysis capabilities exist for visualizing the far-field in polar, 2D, and 3D plots.




Figure 4: A 3D far-field polar plot of the loudspeaker sensitivity at 3000 Hz. From the Vented Loudspeaker Enclosure model found in the application library.

ACOUSTIC-STRUCTURE INTERACTION

The Acoustic-Structure Interaction branch () has interfaces that apply to phenomena where the fluid's pressure causes a load on the solid domain, and the structural acceleration affects the fluid domain across the fluid-solid boundary.

The physics interfaces under this branch are the:

- Acoustic-Solid Interaction, Frequency Domain () and Acoustic-Solid Interaction, Transient () multiphysics interfaces.
- Acoustic-Shell Interaction, Frequency Domain () and Acoustic-Shell Interaction, Transient () multiphysics interfaces.
- Acoustic-Piezoelectric Interaction, Frequency Domain () and Acoustic-Piezoelectric Interaction, Transient () multiphysics interfaces, which support solving and modeling the electric field in a piezoelectric material. The piezoelectric coupling can be in stress-charge or strain-charge form.
- Solid Mechanics (Elastic Waves) (), for modeling elastic waves in solids.
- Poroelastic Waves (), for precisely modeling the propagation of sound in
 a porous material. It includes the two-way coupling between deformation of
 the solid porous matrix and the pressure waves in the saturating fluid. The
 physics interface solves Biot's equations in the frequency domain. It includes
 two formulations for the loss mechanisms. The Biot (viscous losses) for
 modeling rocks and soils and the Biot-Allard (thermal and viscous losses) for
 sound absorbing materials in air.
- Acoustic-Solid-Poroelastic Waves Interaction () and Acoustic-Poroelastic Waves Interaction () multiphysics interfaces.
- The Pipe Acoustics, Transient () and the Pipe Acoustics, Frequency Domain () interfaces are available with the addition of the Pipe Flow Module. These physics interfaces are used for modeling the propagation of sound waves in 1D flexible pipe systems. The equations are formulated in a general way to include the effects of the pipe wall compliance and allow the possibility of a stationary background flow.

The multiphysics interfaces consist of two or more single physics, for example, Pressure Acoustics, Frequency Domain and Solid Mechanics together with a multiphysics coupling, here the Acoustic-Structure Boundary coupling. Many more couplings are supported, for example, coupling Pressure Acoustics to Membrane or Multibody Dynamics interfaces.

AEROACOUSTICS

Detailed convected acoustic (flow borne noise/sound) models to simulate the one-way interaction of a background fluid flow with an acoustic field is modeled

using the physics interfaces found under the Aeroacoustics branch (). The coupling between the fluid mechanics and the acoustics is based on solving the set of linearized governing equations using stabilized finite elements methods. In this way, you solve for the acoustic variations of the acoustic variables on top of a stationary background mean flow. Different physics interfaces exist that solve the governing equations under various physical approximations.

- The Linearized Navier-Stokes, Frequency Domain () and Linearized Navier-Stokes, Transient () interfaces are used for aeroacoustic simulations that can be described by the linearized Navier-Stokes equations solving for the acoustic variations in pressure, velocity, and temperature.
- The Linearized Euler, Frequency Domain interface () and the Linearized Euler, Transient interface () solve the Linearized Euler equations. They are used to compute the acoustic variations in density, velocity, and pressure in the presence of a stationary background mean-flow that is well approximated by an ideal gas flow.
- The Linearized Potential Flow, Frequency Domain () and the Linearized Potential Flow, Transient () interfaces model the interaction of a stationary background potential flow with an acoustic field. These physics interfaces are only suited for cases where the flow is inviscid and, being irrotational, has no vorticity. The background flow is typically solved for using the Compressible Potential Flow interface ().
- The Linearized Potential Flow, Boundary Mode interface () is used to study boundary mode acoustic problems in a background flow field. It is typically used to define sources at the inlet of ducts.

THERMOVISCOUS ACOUSTICS

The physics interfaces under the Thermoviscous Acoustics branch ())) are used to accurately model acoustics in geometries with small dimensions. Near walls a viscous and thermal boundary layer (penetration depth) exist. Here viscous losses due to shear and thermal conduction become important because of large gradients. For this reason, it is necessary to include thermal conduction effects and viscous losses explicitly in the governing equations. Thermoviscous acoustics is, for example, used when modeling the response of small transducers like microphones and receivers. Other applications include analyzing feedback in hearing aids and in mobile devices, or studying the damped vibrations of MEMS structures.

Because a detailed description is needed to model thermoviscous acoustics, the physics interface simultaneously solves for the acoustic pressure p, the particle velocity vector \mathbf{u} , and the acoustic temperature variation T.

In the Thermoviscous Acoustics, Frequency Domain interface ()), the governing equations are implemented in the time-harmonic formulation and solved in the frequency domain. The interface is given in the scattered field formulation. Both mechanical and thermal boundary conditions exist. The interface exists in a time domain formulation, the Thermoviscous Acoustics, Transient interface ()). The Thermoviscous Acoustics, Boundary Mode interface is () is used to compute and identify propagating and non-propagating modes in waveguides and ducts. The interface performs a boundary mode analysis on a boundary, inlet, or cross section of a waveguide or duct of small dimensions. Several multiphysics interfaces involving thermoviscous acoustics also exists:

- Acoustic-Thermoviscous Acoustic Interaction, Frequency Domain multiphysics interface ()))) that includes Pressure Acoustics, Frequency Domain and the Acoustics-Thermoviscous Acoustics Boundary coupling feature. Coupling the thermoviscous acoustics domain to a pressure acoustics domain is also straightforward, with the predefined multiphysics condition.
- A Thermoviscous Acoustic-Solid Interaction, Frequency Domain multiphysics interface () is available to solve coupled vibro-acoustic problems. This can, for example, be used to model small electroacoustic transducers or damping in MEMS devices. It includes Solid Mechanics and the predefined multiphysics coupling to Thermoviscous Acoustics.
- The Thermoviscous Acoustic-Shell Interaction, Frequency Domain multiphysics interface () is used for modeling the interactions between shells and acoustics in small dimensions. This can, for example, be used to analyze the damped vibrations of shells in hearing aids and prevent feedback problems.




Figure 5: Deformation of the diaphragm (or membrane) at 12 kHz in the Axisymmetric Condenser Microphone model found in the application library.

ULTRASQUND

One physics interface exists under the Ultrasound branch (): the Convected Wave Equation, Time Explicit () interface which is used to solve large transient linear acoustic problems containing many wavelengths in a stationary background flow. In general, the interface is suited for modeling the propagation of acoustic signals over large distances relative to the wavelength, for example, linear ultrasound problems. The interface includes absorbing layers that are used to set up effective nonreflecting like boundary conditions. The interface is based on the discontinuous Galerkin method and uses a time explicit solver. The method is very memory lean. Application areas include ultrasound flow meters and other ultrasound sensors where time of flight is an important parameter.

GEOMETRICAL ACOUSTICS

Two physics interfaces exist under the Geometrical Acoustics branch: the Acoustic Diffusion Equation interface and the Ray Acoustics interface. Both are used to model acoustics in the high frequency limit where the wavelength is significantly smaller than the characteristic geometrical features.

The Ray Acoustics physics interface is used to compute the trajectories, phase, and intensity of acoustic rays. The interface can be used to model room acoustic problems like concert halls, lecture halls or car cabins, and many outdoor and underwater environments. The interface has a dedicated receiver data set that is used to create an impulse response plot.

The Acoustic Diffusion Equation interface solves a diffusion equation for the acoustic energy density distribution for modeling indoor room acoustics in buildings and concert halls. It is also known as energy finite elements.

Physics Interface Guide by Space Dimension and Study Type

The table below lists the physics interfaces available specifically with this module in addition to those in the COMSOL Multiphysics basic license.

PHYSICS INTERFACE	ICON	TAG	SPACE DIMENSION	AVAILABLE STUDY TYPE		
)))) Acoustics						
Pressure Acoustics						
Pressure Acoustics, Frequency Domain ¹		acpr	all dimensions	eigenfrequency; frequency domain; frequency-domain modal; mode analysis (2D and ID axisymmetric models only)		
Pressure Acoustics, Transient	(3)	actd	all dimensions	eigenfrequency; frequency domain; frequency-domain modal; time dependent; time-dependent modal; modal reduced order model; mode analysis (2D and ID axisymmetric models only)		
Pressure Acoustics, Boundary Mode		acbm	3D, 2D axisymmetric	mode analysis		
Pressure Acoustics, Boundary Elements		pabe	3D, 2D	frequency domain		
Pressure Acoustics, Time Explicit		pate	3D, 2D, 2D axisymmetric	time dependent		
Acoustic-Structure Interaction						
Acoustic-Solid Interaction, Frequency Domain ⁴)))\[\begin{align*} \text{\tin}\text{\tetx{\text{\tetx{\text{\text{\text{\text{\texi}\text{\texi}\text{\text{\text{\tin}\text{\text{\text{\text{\text{\texi}\text{\text{\texit{\text{\texi}\text{\texi}\tittt{\texitit}\\\ \tittt{\text{\texi}\	_	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency-domain modal		
Acoustic-Solid Interaction, Transient ⁴	W))	_	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency-domain modal; time dependent; time-dependent modal; modal reduced order model		

PHYSICS INTERFACE	ICON	TAG	SPACE DIMENSION	AVAILABLE STUDY TYPE
Acoustic-Shell Interaction, Frequency Domain ^{2,4}	****		3D	eigenfrequency; frequency domain; frequency-domain modal
Acoustic-Shell Interaction, Transient ² , 4	w)))	_	3D	eigenfrequency; frequency domain; frequency-domain modal; time dependent; time-dependent modal; modal reduced order model
Acoustic-Piezoelectric Interaction, Frequency Domain ⁴	111	_	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency-domain modal
Acoustic-Piezoelectric Interaction, Transient ⁴	((w	_	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency-domain modal; time dependent; time-dependent modal; modal reduced order model
Solid Mechanics (Elastic Waves) ¹		solid	3D, 2D, 2D axisymmetric	Placeholder for Solid Mechanics, see below
Poroelastic Waves	\$	pelw	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency-domain modal
Acoustic-Elastic Waves Interaction ⁴))) T	_	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency-domain modal
Acoustic-Poroelastic Waves Interaction ⁴)))🔡	_	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency-domain modal
Pipe Acoustics, Frequency Domain ³	()(RI	pafd	3D, 2D	eigenfrequency; frequency domain
Pipe Acoustics, Transient ³	(m)))	patd	3D, 2D	time dependent
Meroacoustics	•			
Linearized Euler, Frequency Domain	11)	lef	3D, 2D axisymmetric, 2D, and 1D	frequency domain; eigenfrequency

PHYSICS INTERFACE	ICON	TAG	SPACE DIMENSION	AVAILABLE STUDY TYPE
Linearized Euler, Transient	201)	let	3D, 2D axisymmetric, 2D, and 1D	time dependent
Linearized Potential Flow, Frequency Domain))))	ae	all dimensions	frequency domain; mode analysis (2D and 1D axisymmetric models only)
Linearized Potential Flow, Transient	w)))	aetd	all dimensions	frequency domain; time dependent mode analysis (2D and ID axisymmetric models only)
Linearized Potential Flow, Boundary Mode		aebm	3D, 2D axisymmetric	mode analysis
Compressible Potential Flow	***)	cpf	all dimensions	stationary; time dependent
Linearized Navier-Stokes, Frequency Domain	100	Insf	3D, 2D axisymmetric, 2D, and 1D	frequency domain; eigenfrequency
Linearized Navier-Stokes, Transient	ve))	Inst	3D, 2D axisymmetric, 2D, and 1D	time dependent
Thermoviscous Acoustics				
Thermoviscous Acoustics, Frequency Domain))))	ta	all dimensions	eigenfrequency; frequency domain; frequency domain modal; mode analysis (2D and ID axisymmetric models only)
Thermoviscous Acoustics, Transient	v)))	tatd	all dimensions	time domain
Thermoviscous Acoustics, Boundary Mode		tabm	3D, 2D axisymmetric	mode analysis
Acoustic-Thermoviscou s Acoustic Interaction, Frequency Domain ⁴	(1) ¹⁾		3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency domain modal

PHYSICS INTERFACE	ICON	TAG	SPACE DIMENSION	AVAILABLE STUDY TYPE		
Thermoviscous Acoustic-Solid Interaction, Frequency Domain ⁴	****	_	3D, 2D, 2D axisymmetric	eigenfrequency; frequency domain; frequency domain modal		
Thermoviscous Acoustic-Shell Interaction, Frequency Domain ^{2,4}	****	_	3D	eigenfrequency; frequency domain; frequency domain modal		
Ultrasound						
Convected Wave Equation, Time Explicit	w)))	cwe	3D, 2D. 2D axisymmetric	time dependent		
€ Geometrical Aco	Geometrical Acoustics					
Ray Acoustics		rac	3D, 2D, 2D axisymmetric	ray tracing; time dependent		
Acoustic Diffusion Equation	HIE HE	ade	3D	eigenvalue; stationary; time dependent		
Structural Mechanic	s					
Solid Mechanics ¹		solid	3D, 2D, 2D axisymmetric	stationary; eigenfrequency; prestressed analysis, eigenfrequency; time dependent; time-dependent modal; frequency domain; frequency-domain modal; prestressed analysis, frequency domain; modal reduced order model		
Piezoelectric Devices ⁴	*		3D, 2D, 2D axisymmetric	stationary; eigenfrequency; time dependent; frequency domain; small-signal analysis, frequency domain; prestressed analysis, eigenfrequency; prestressed analysis, frequency domain		

PHYSICS INTERFACE	ICON	TAG	SPACE DIMENSION	AVAILABLE STUDY TYPE
Magnetostriction	<u>f</u>	_	3D, 2D, 2D axisymmetric	stationary; eigenfrequency; time dependent; frequency domain; small-signal analysis, frequency domain; prestressed analysis, eigenfrequency; prestressed analysis, frequency domain

 $^{^{}m l}$ This physics interface is included with the core COMSOL package but has added functionality for this module.

² Requires both the Structural Mechanics Module and the Acoustics Module.

³Requires both the Pipe Flow Module and the Acoustics Module.

⁴ This physics interface is a predefined multiphysics coupling that automatically adds all the physics interfaces and coupling features required.

The Application Libraries Window

To open an Acoustics Module application library model, click Blank Model in the New screen. Then in the File menu click Application Libraries . In the Application Libraries window that opens, expand the Acoustics Module folder and browse or search the contents.

Click Open Application open it in COMSOL Multiphysics or click Open PDF Document to read background information including the step-by-step instructions to build it. The MPH-files in the COMSOL application library can have two formats — Full MPH-files or Compact MPH-files.

- Full MPH-files, including all meshes and solutions. In the Application Libraries window these appear with the icon or for runnable applications, this icon (•). If the MPH-file's size exceeds 25MB, a tip with the text "Large file" and the file size appears when you position the cursor at the model's node in the Application Libraries tree.
- Compact MPH-files with all settings for the model but without built meshes and solution data to save space (a few MPH-files have no solutions for other reasons). You can open these to study the settings and to mesh and re-solve the applications. It is also possible to download the full versions—with meshes and solutions—of most of these when you update your application library. These appear in the Application Libraries window with the o icon and for runnable applications, this icon (o). If you position the cursor at a compact file in the Application Libraries window, a No solutions stored message appears. If a full MPH-file is available for download, the corresponding node's context menu includes a Download File with Solutions (o) option.

To check all available Application Libraries updates, select Update COMSOL Application Library () from the File>Help menu (Windows users) or from the Help menu (Mac and Linux users).

Get started with the Example: Absorptive Muffler. The last section, Additional Examples from the Application Libraries, provides a brief overview of some of the other models also available in the Acoustics Module Application Libraries.

Basics of Acoustics

Acoustics is the physics of sound. Sound is the sensation, as detected by the ear, of very small rapid changes in the acoustic pressure p above and below a static value p_0 . This static value is the atmospheric pressure (about 100,000 pascals).

The amplitude of the small pressure variations that can be detected by the human ear vary from roughly $2\cdot 10^{-5}$ Pa at the hearing threshold to 20 Pa for jet engine noise. The amplitude at normal speech levels is about 0.02 Pa. The amplitudes described here are often given on a the logarithmic decibel scale, relative to the hearing threshold value of $2\cdot 10^{-5}$ Pa, in units of dB SPL.

The acoustic pressure variations are typically described as pressure waves propagating in space and time. The wave crests are the pressure maxima while the troughs represent the pressure minima.

In more general terms, sound is created when the fluid is disturbed by a source. An example is a vibrating object, such as a speaker cone in a sound system. It is possible to see the movement of a bass speaker cone when it generates sound at a very low frequency. As the cone moves forward it compresses the air in front of it, causing an increase in air pressure. Then it moves back past its resting position and causes a reduction in air pressure. This process continues, radiating a wave of alternating high and low pressure at the speed of sound.

The frequency f (SI unit: Hz = 1/s) is the number of vibrations (pressure peaks) perceived per second and the wavelength λ (SI unit: m) is the distance between two such peaks. The speed of sound c (SI unit: m/s) is given as the product of the frequency and the wavelength, $c = \lambda f$. It is often convenient to define the angular frequency ω (SI unit: rad/s) of the wave, which is $\omega = 2\pi f$, and relates the frequency to a full 360° phase shift. The wave number k (SI unit: rad/m) is defined as $k = 2\pi/\lambda$. The wave number, which is the number of waves over a specific distance, is also usually defined as a vector \mathbf{k} , such that it also contains information about the direction of propagation of the wave, with $|\mathbf{k}| = k$. In general, the relation between the angular frequency ω and the wave number k is called the dispersion relation; for simple fluids it is $\omega/k = c$.

Governing Equations

The equations that describe the propagation of sound in fluids are derived from the governing equations of fluid flow. That is, conservation of mass, which is described by the continuity equation; the conservation of momentum, which is often referred to as the Navier-Stokes equations; an energy conservation equation; the constitutive equations of the model; and an equation of state to describe the relation between thermodynamic variables. In the classical case of pressure acoustics, which describes most acoustic phenomena accurately, the flow is

assumed lossless and adiabatic, viscous effects are neglected, and a linearized isentropic equation of state is used.

Under these assumptions, the acoustic field is described by one variable, the pressure p (SI unit: Pa), and is governed by the wave equation

$$\frac{1}{\rho_0 c^2} \frac{\partial^2 p}{\partial t^2} + \nabla \cdot \left(-\frac{1}{\rho_0} \nabla p \right) = 0$$

where t is time (SI unit: s), ρ_0 is the density of the fluid (SI unit: kg/m³), and c is the (adiabatic) speed of sound (SI unit: m/s).

Acoustic problems often involve simple harmonic waves such as sinusoidal waves. More generally, any signal may be expanded into harmonic components via its Fourier series. The wave equation can then be solved in the frequency domain for one frequency at a time. A harmonic solution has the form

$$p(\mathbf{x}, t) = p(\mathbf{x})\sin(\omega t)$$

where the spatial $p(\mathbf{x})$ and temporal $\sin(\omega t)$ components are split. The pressure may be written in a more general way using complex variables

$$p(\mathbf{x},t) = p(\mathbf{x})e^{i\omega t} \tag{1}$$

where the actual (instantaneous) physical value of the pressure is the real part of Equation 1. Using this assumption for the pressure field, the time-dependent wave equation reduces to the well-known Helmholtz equation

$$\nabla \cdot \left(-\frac{1}{\rho_0} \nabla p \right) - \frac{\omega^2}{\rho_0 c^2} p = 0 \tag{2}$$

In the homogeneous case one simple solution to the Helmholtz equation (Equation 2) is the plane wave

$$p = P_0 e^{i(\omega t - \mathbf{k} \cdot \mathbf{x})} \tag{3}$$

where P_0 is the wave amplitude, and it is moving in the **k** direction with angular frequency ω and wave number $k = |\mathbf{k}|$.

In most practical situations an exact analytical solution to Equation 2 does not exist. Solving the equation requires a numerical approach using simulations.

Numerical Methods

As mentioned, solving the governing equations for the acoustic problems analytically, like for example, the Helmholtz equation (Equation 2), is only possible in a few simple situations. In order to solve real life industrial problems, which can

very well be multiphysics problems involving several coupled physics, numerical methods are necessary. This is the job of COMSOL Multiphysics. In the Acoustics Module most of the physics interfaces are based on the finite element method (FEM). In order to extend the range of models that can be solved the Acoustics Module also includes the Pressure Acoustics, Boundary Elements interface based on BEM, two interfaces based on the discontinuous Galerkin (dG-FEM) method, and Ray Acoustics that uses a ray tracing method.

Solving a model using the FEM requires a computational mesh. The solution is approximated on each mesh element (the finite elements) by a shape function (a local basis or interpolation function). Setting up this system of mesh elements and local shape functions leads to a discrete vector-matrix problem that needs to be solved. After solving the matrix problem with an adequate method the solution to the original problem can be reconstructed. When solving wave problems numerically one should be aware of the time and length scales involved in the problem, as will be discussed below.

Length and Time Scales

When solving acoustic problems, it is important to think about the different basic length and time scales involved in the system. Some of the scales are set by the physics of the problem, while others are set by the numerical solution method. The relative size of these scales may influence the accuracy of the solution but also the selection of the physics interface used to model the problem.

When working with acoustics in the frequency domain, that is, solving the Helmholtz equation, only one time scale T exists (the period) and it is set by the frequency, T=1/f. Several length scales exist: the wavelength $\lambda=c/f$, the smallest geometric dimension L_{\min} , the mesh size h, and the thickness of the acoustic boundary layer δ (the latter is discussed in Models with Losses). In order to get an accurate solution, the mesh should be fine enough to both resolve the geometric features and the wavelength. As a rule of thumb, the maximal mesh size should be less than or equal to λ/N , where N is a number between 5 and 10, and depends on the spatial discretization.

Note that when the wavelength becomes smaller than the characteristic length scale in the model, the two interfaces in Geometrical Acoustics can be used. The equations solved here do not require the same mesh constraints and can be used to model much larger systems (measured in wavelengths) compared to solving, for example, the Helmholtz equation.

For transient acoustic problems the same considerations apply. However, several new time scales are also introduced. One is given by the frequency contents of the signal and by the desired maximal frequency resolution: $T = 1/f_{\text{max}}$. The other is given by the size of the time step Δt used by the numerical solver. A condition on

the so-called CFL number dictates the relation between the time step size and the minimal mesh size h_{\min} . The CFL number is defined as

$$CFL = \frac{c\Delta t}{h_{\min}} \tag{4}$$

where c is the speed of sound in the system. For all the transient interfaces available with the Acoustics Module the solver is automatically set up to meet the CFL criterion. The user is only required to enter the maximal frequency $f_{\rm max}$ to be resolved by the model.

In order to run accurate acoustic simulations it is important to think about these physical and numerical scales and about their influence on the convergence and correctness of the numerical solution. A good practical approach is to test the robustness of a solution compared to changes in the mesh in all cases and the numerical time stepping in the transient problems. If some measure of the solution, within a given accuracy range, changes when the mesh is refined then the mesh was probably not good enough.

Boundary Conditions

Boundary conditions define the nature of the boundaries of the computational domain. Some define real physical obstacles, like a sound hard wall or a moving interface. Others, called artificial boundary conditions, are used to truncate the domain. The artificial boundary conditions are, for example, used to simulate an open boundary where no sound is reflected. It may also mimic a reacting boundary such as a perforated plate.

Elastic Waves

The propagation of sound in solids happens through small-amplitude elastic oscillations of the solids shape and structure. These elastic waves are transmitted to surrounding fluids as ordinary sound waves. Through acoustic-structure interaction, the fluid's pressure causes a fluid load on the solid domain, and the structural acceleration affects the fluid domain as a normal acceleration across the fluid-solid boundary.

The Acoustics Module has the Poroelastic Waves interface available to model poroelastic waves that propagate in porous materials. These waves result from the complex interaction between acoustic pressure variations in the saturating fluid and the elastic deformation of the solid porous matrix.

Models with Losses

In order to accurately model acoustics in geometries with small dimensions, it is necessary to include thermal conduction effects and viscous losses explicitly in the governing equations. Near walls, viscosity and thermal conduction become important because the acoustic field creates a viscous and a thermal boundary layers where losses are significant. A detailed description is needed to model these phenomena; the dedicated Thermoviscous Acoustics, Frequency Domain interface solves the full linearized Navier-Stokes, continuity, and energy equations simultaneously. The physics interface solves for the acoustic pressure p, the particle velocity vector \mathbf{u} , and the acoustic temperature variation T. These are the acoustic variations on top of the mean background values.

The length scale at which the thermoviscous acoustic description is necessary is given by the thickness of the viscous (v) and thermal (th) boundary layers

$$\delta_{\rm v} = \sqrt{\frac{\mu}{\pi f \rho}} \qquad \delta_{\rm th} = \sqrt{\frac{k}{\pi f \rho C_{\rm p}}}$$


where μ is the dynamic viscosity, k is the coefficient of thermal conduction, and C_p is the specific heat capacity at constant pressure. These two length scales define an acoustic boundary layer that needs to be resolved by the computational mesh.

Another way to introduce losses in the governing equations is to use the equivalent fluid models available in the pressure acoustics interfaces. In a homogenized way, this introduces attenuation properties to the bulk fluid that mimic different loss mechanisms. This is in contrast to the thermoviscous acoustics interfaces that model losses explicitly where they happen, that is, in the acoustic boundary layer near walls. The fluid models include losses due to bulk thermal conduction and viscosity (in the main Pressure Acoustics domain feature), models for simulating the damping in certain porous materials (in the Poroacoustics domain feature), and models to mimic the boundary absorption losses in long narrow ducts (the Narrow Region Acoustics domain feature). When applicable, the equivalent fluid models are computationally much less heavy than, for example, solving a corresponding full poroelastic model.

Geometrical Acoustics

At high frequencies when the wavelength is much smaller than the characteristic geometric features it is impractical to solve acoustic problems using pressure acoustics. Here other methods are used like, for example, ray methods or energy diffusion analogies. These are known as geometrical acoustics methods and are used for modeling room acoustics, concert hall acoustics, and outdoor

propagation over large distances. The Geometrical Acoustics branch includes the Ray Acoustics and the Acoustic Diffusion Equation interfaces.



Sound pressure level and energy flux inside a two story house modeled using the Acoustic Diffusion Equation physics interface. Figure taken from the One-Family House Acoustics model found in the Application Gallery on comsol.com.




Figure 6: Ray tracing model of a small concert hall including the ray location at 0.02 s, the SPL distribution at the seat locations, and a schematic plot of the impulse response (inset). Figure taken from the Small Concert Hall Acoustics model found in the Application Gallery on comsol.com.

Example: Absorptive Muffler

This example describes the pressure-wave propagation in a muffler for an internal combustion engine. The approach used here is generally applicable to analyzing the damping of propagating pressure waves as well as determining the transmission properties of a given system. The model uses the port boundary conditions to model the inlet and outlet of the muffler. The model shows how to analyze both inductive and resistive damping in pressure acoustics. The main output is the transmission loss for the frequency range 50 Hz–1500 Hz. It is represented both as a continuous curve and given in 1/3 octave bands.

Model Definition

The muffler, schematically shown in the figure below, consists of a 24-liter resonator chamber with a section of the centered exhaust pipe included at each end. The model is first set up assuming that the chamber is empty. Secondly, it is lined with 15 mm of absorbing glass wool.




Figure 7: Geometry of the lined muffler, the liner is the outer layer in the main muffler volume. The exhaust fumes enter through the left pipe and exit through the right pipe.

Domain Equations

This model solves the problem in the frequency domain using the Pressure Acoustics, Frequency Domain interface. The model equation is a slightly modified version of the Helmholtz equation for the acoustic pressure p:

$$\nabla \cdot \left(-\frac{\nabla p}{\rho} \right) - \frac{\omega^2 p}{c^2 \rho} = 0$$

where ρ is the density, c is the speed of sound, and ω gives the angular frequency. The subscript c refers to that these can be complex valued.

In the absorbing glass wool, modeled as a Poroacoustics domain, the damping enters the equation as a complex speed of sound, $c_{\rm c} = \omega/k_{\rm c}$, and a complex density, $\rho_{\rm c} = k_{\rm c} \, Z_{\rm c}/\omega$, where $k_{\rm c}$ is the complex wave number and $Z_{\rm c}$ equals the complex impedance. This is a so-called equivalent fluid model for the porous domain where the losses are modeled in a homogenized way.

For a highly porous material with a rigid skeleton, the classical empirical Delany and Bazley model estimates these parameters as functions of frequency and flow resistivity. Using the original coefficients of Delany and Bazley (Ref. 1), the expressions are

$$\begin{split} & k_{\rm c} = k_{\rm a} \cdot \left(1 + 0.098 \cdot \left(\frac{\rho_{\rm a} f}{R_{\rm f}}\right)^{-0.7} - i \cdot 0.189 \cdot \left(\frac{\rho_{\rm a} f}{R_{\rm f}}\right)^{-0.595}\right) \\ & Z_{\rm c} = Z_{\rm a} \cdot \left(1 + 0.057 \cdot \left(\frac{\rho_{\rm a} f}{R_{\rm f}}\right)^{0.734} - i \cdot 0.087 \cdot \left(\frac{\rho_{\rm a} f}{R_{\rm f}}\right)^{-0.732}\right) \end{split}$$

where $R_{\rm f}$ is the flow resistivity, and where $k_{\rm a}=\omega/c_{\rm a}$ and $Z_{\rm a}=\rho_{\rm a}c_{\rm a}$ are the free-space wave number and impedance of air, respectively. This model is the default selected for the Delany-Bazley-Miki model in the Poroacoustics domain feature. You can find flow resistivities in tables, see for example Ref. 3 or by measuring it. For glass-wool-like materials, Bies and Hansen (Ref. 2) give an empirical correlation

$$R_{\rm f} = \frac{3.18 \cdot 10^{-9} \cdot \rho_{\rm ap}^{1.53}}{d_{\rm ay}^2}$$

where ρ_{ap} is the material's apparent density and d_{av} is the mean fiber diameter. This model uses a lightweight glass wool with $\rho_{ap} = 12 \text{ kg/m}^3$ and $d_{av} = 10 \text{ }\mu\text{m}$.

Note: The Delany-Bazley model is valid for values of $(\rho_f f)/R_f$ up to $(\rho_f f)/R_f \approx 1$, so the upper frequency limit of 1500 Hz ensures that the poroacoustics model applies. Other variants of the Delany-Bazley model are built into the Acoustics Module, these have different validity regions or are used for other fibrous materials. For example, the Miki parameters can be selected, they extend the region of applicability of the Delany-Bazley constants.

Boundary Conditions

- At the solid boundaries, which are the outer walls of the resonator chamber and the pipes, the model uses sound hard (wall) boundary conditions. The condition imposes that the normal velocity at the boundary is zero.
- The model uses port boundary conditions to model the inlet and outlet of the muffler. In waveguides, the port conditions are superior to radiation condition as they can capture complex wave fields that involve several propagating modes. In this model only plane waves propagation is considered. This means that only one port condition needs to be added at each end. The port uses a plane wave (0,0) mode. If the analysis is carried out above the cutoff frequency of the first non-plane mode (above 2540 Hz), then simply add more port conditions at the inlet and outlet to capture these modes. Note that each port condition generates a post processing variable that defines the cutoff frequency of its mode, for example, for Port 1 the variable is acpr.port1.fc. The plane wave cutoff frequency is of course 0 Hz.

Results and Discussion

The pressure distribution in the absorptive muffler without the lining material is shown in Figure 8 for the frequency f = 1500 Hz. From the figure it is seen that at this frequency not only longitudinal standing waves exist but also transverse modes are present.






Figure 8: The pressure distribution in the absorptive muffler without the liner is shown for f = 1500 Hz.

An important parameter for a muffler is the transmission loss or attenuation. It is defined as the ratio between the incoming and outgoing acoustic energy. The attenuation or transmission loss L (in dB) of the acoustic energy is defined by

$$L = 10 \log \left(\frac{P_{\rm in}}{P_{\rm out}} \right)$$

Here $P_{\rm in}$ and $P_{\rm out}$ denote the incoming power at the inlet and the outgoing power at the outlet, respectively. These values are readily defined by the port boundary conditions as acpr.port1.P_in and acpr.port2.P_out and can be directly used in postprocessing.




Figure 9: Comparison of the transmission loss as function of frequency for the empty muffler and the muffler with absorptive lining. (top) The transmission loss depicted as a continuous curve, and (bottom) The same data but depicted in 1/3 octave bands.

Figure 9 (top and bottom) shows the result of a parametric frequency study. The two graphs represent the case of an empty muffler without any absorbing lining material (blue lines) and the case with a layer of glass wool lining on the chamber's walls (green lines). The first four dips are due to longitudinal resonances. In the muffler with absorbing lining the dips are still present, but the general trend is that the higher the frequency, the better the damping. In the top figure the transmission loss is depicted as a continuous curve (pure tone sweep) while it is depicted in 1/3 octave bands in the bottom figure. Both graphs are created using the Octave Band Plot of the Acoustics Module.

The graph for the undamped muffler shows that damping works rather well for most low frequencies. At frequencies higher than approximately 1250 Hz, the plot's behavior is more complicated and there is generally less damping. This is because the tube supports not only longitudinal resonances but also cross-sectional propagating modes, for such frequencies. Not very far above this frequency a whole range of modes that are combinations of this propagating mode and the longitudinal modes participate, making the damping properties increasingly unpredictable. For an analysis of these modes, see the related model *Eigenmodes in a Muffler*. The glass-wool lining improves attenuation at the resonance frequencies as well as at higher frequencies.

The flow of energy in the muffler without the liner is shown in Figure 10 at 1500 Hz. The plot represents the intensity field depicted as streamlines. The intensity field is per definition the time average of the energy flux (instantaneous intensity) and thus represents the average energy flow in the system. Here from the inlet to the outlet. Change between solutions and frequencies to study and visualize the muffler's sound-absorbing properties.




Figure 10: Intensity streamlines at 1500 Hz without the liner.

References

- 1. M. A. Delany and E. N. Bazley, "Acoustic Properties of Fibrous Absorbent Materials," *Appl. Acoust.*, vol. 3, pp. 105–116, 1970.
- 2. D. A. Bies and C. H. Hansen, "Flow Resistance Information for Acoustical Design," *Appl. Acoust.*, vol. 13, pp. 357–391, 1980.
- 3. T. J. Cox and P. D'Antonio, *Acoustic Absorbers and Diffusers*, Second Edition, Taylor and Francis, 2009.

Step-by-Step Instructions

The first part of the model instructions (below) describe how to set up and postprocess the Absorptive Muffler model. For simplicity the geometry sequence is imported. They are followed by the Geometry Sequence Instructions section where the geometry is set up.

Model Wizard

The instructions take you through two versions of the model, first with a completely hollow chamber with rigid walls, then where the chamber is lined with glass wool.

Note: These instructions are for the user interface on Windows but apply, with minor differences, also to Linux and Mac.

I To start the software, double-click the COMSOL icon on the desktop. When the software opens, you can choose to use the Model Wizard to create a new COMSOL model or Blank Model to create one manually. For this tutorial, click the Model Wizard button.

If COMSOL is already open, you can start the Model Wizard by selecting New \bigcap from the File menu and then click Model Wizard \bigcirc .

The Model Wizard guides you through the first steps of setting up a model. The next window lets you select the dimension of the modeling space.

- **2** In the Space Dimension window click the 3D button **.**
- 3 In the Select Physics tree under Acoustics>Pressure Acoustics, click Pressure Acoustics, Frequency Domain (acpr) → To add the physics interface, double-click it, click Add, or right-click and select → Add Physics.
- 4 Click Study 🖨.
- 5 On the Select Study window under General Studies, click Frequency Domain
- 6 Click Done **☑**.

Global Definitions

Note: The location of the text files used in this exercise vary based on the installation. For example, if the installation is on your hard drive, the file path might be similar to C:\Program Files\COMSOL53a\applications\.

Parameters


I On the Home toolbar click Parameters P_i and select Parameter l P_i .

Note: On Linux and Mac, the Home toolbar refers to the specific set of controls near the top of the Desktop.

2 Go to the Settings window for Parameters. Under Parameters click Load from File ...

3 Browse to the application library folder (Acoustics_Module\Automotive) and double-click the file absorptive muffler parameters.txt.

The parameters define the physical values and the geometrical dimensions of the system. The geometry is now parameterized and simply changing the value of a dimension in the parameters list updates the geometry automatically.




Geometry I

- In the Model Builder window, under Component 1 (comp1) click Geometry 1.
- 2 In the Settings window for Geometry, locate the Units section.
- **3** From the Length unit list, choose mm.

To save some time, import the geometry sequence from a file. The instructions for setting up the geometry can be found in the Geometry Sequence Instructions section at the bottom of this document.

- In the Geometry toolbar, click Insert Sequence.
- 2 Browse to the model's Application Libraries folder and double-click the file absorptive_muffler_geom_sequence.mph.

3 In the Geometry toolbar, click Build All.



Having imported the geometry it can be easily modified as it is parameterized. Simply change the value of a dimension in the parameters list, this will update the geometry automatically. The imported geometry parameters are automatically added to the Parameters 1 node.

Definitions

Create selections for the inlet and outlet of the muffler.


Explicit I

- I On the Definitions toolbar click Explicit 🔪.
- **2** Go to the Settings window for Explicit. Enter Inlet in the Label field (replace the default).
- **3** Under Input Entities from the Geometric entity level list, choose Boundary.
- 4 Select Boundary 1 only.

Explicit 2


I On the Definitions toolbar click Explicit \S .


- 2 Go to the Settings window for Explicit. Enter Outlet in the Label field (replace the default).
- **3** Under Input Entities from the Geometric entity level list, choose Boundary.
- 4 Select Boundary 28 only.




Add Material

- On the Home toolbar click Add Material :: .
- 2 Go to the Add Material window. In the tree under Built-In click Air :: .
- 3 In the Add material window, clickAdd to Component.
- 4 Under Materials click Air ## to look at the Material Contents in the Settings window.





The green check marks indicate which material parameters are necessary in the model.



Note: By default the first material added applies to all domains so the geometric scope settings do not need to be changed.

In the second version of this model, a lining material is inserted in Domain 2. For now, the muffler is completely hollow.


Pressure Acoustics, Frequency Domain

Pressure Acoustics 1

- In the Model Builder window, under Component 1 (comp1)>Pressure Acoustics, Frequency Domain (acpr) click Pressure Acoustics 1.
- 2 In the Settings window for Pressure Acoustics, locate the Model Input section.
- **3** In the *T* text field, type T0.
- 4 In the pA text field, type p0.

Use the Port boundary condition to define the inlet and outlet. The port condition is superior to the classical radiation condition in wave guide configurations. This is particularly the case when non-plane wave modes start to propagate. This happens above the first cutoff frequency. For the present model the cutoff frequency for the first non-plane mode (m = 1 and n = 0) is at 2514 Hz which is much higher than the frequencies studied here. If the frequency analysis is extended above this frequency, then add more port conditions to capture these

modes. Note that the variable acpr.port1.fc gives the cutoff frequency of the modes (here for the mode defined on the Port 1 condition).




Port 1


- In the Physics toolbar, click Boundaries and choose Port.
- 2 In the Settings window for Port, locate the Boundary Selection section.
- **3** From the Selection list, choose Inlet.
- **4** Locate the Port Properties section. From the Type of port list, choose Circular.

5 Locate the Incident Mode Settings section. In the Aⁱⁿ text field, type p in.

Circular Port Reference Axis I

- Right-click Port 1 and choose Circular Port Reference Axis.
- 2 In the Settings window for Circular Port Reference Axis, locate the Point Selection section.
- 3 Click Clear Selection.
- 4 Select Points 1 and 4 only.
 Select two points that define a reference axis for the azimuthal angle. The setting is in general necessary when higher order azimuthal modes are used and/or necessary.





Port 2

- In the Physics toolbar, click Boundaries and choose Port.
- 2 In the Settings window for Port, locate the Boundary Selection section.
- **3** From the Selection list, choose Outlet.

4 Locate the Port Properties section. From the Type of port list, choose Circular.

Circular Port Reference Axis I

- Right-click Port 2 and choose Circular Port Reference Axis.
- 2 In the Settings window for Circular Port Reference Axis, locate the Point Selection section.
- 3 Click Clear Selection.
 Select two points at the outlet in the same way.
- 4 Select Points 37 and 40 only.

Now, add a poroacoustics model for the absorptive liner domain. You will deactivate this domain when configuring the first study step.

Poroacoustics

- On the Physics toolbar click Domains = and choose Poroacoustics =.
- **2** Go to the Settings window for Poroacoustics. Select Domain 2 only.
- 3 In the Settings window for Poroacoustics, locate the Model Input section.
- 4 In the T text field, type T0.
- **5** Locate the Porous Matrix Properties section. From the Porous elastic material list, choose Absorptive Liner (mat2).

The material data for the flow resistivity will now be picked up from the Absorptive Liner material. Enter the data in the material.

Materials

Absorptive Liner (mat2)

- In the Model Builder window, under Component 1 (comp1)>Materials click Absorptive Liner (mat2).
- 2 In the Settings window for Material, locate the Material Contents section.
- **3** In the table, enter the following settings:

PROPERTY	VARIABLE	VALUE	UNIT	PROPERTY GROUP
Flow resistivity	Rf	R_f	Pa·s/m²	Poroacoustics model


Mesh I

Because the geometry is long and slender and it has constant cross sections, an extruded mesh is used. This reduces the number of mesh elements while still retaining the desired mesh resolution of the acoustic field.

Free Triangular I

- I On the Mesh toolbar click Boundary and choose Free Triangular

 Note an also right-click the Mesh node and choose this from the More Operations submenu.
- 2 To more easily locate and select a boundary, click the Wireframe Rendering button 😭 on the Graphics window toolbar.
- **3** Go to the Settings window for Free Triangular. Select Boundaries **6**, **9**, and **16** only.




Size

- Under Mesh 1 click Size ▲.
- **2** Go to the Settings window for Size. Under Element Size click the Custom button.

3 Under Element Size Parameters in the Maximum element size text field, enter 343[m/s]/1500[Hz]/5.

The global maximum element size is set equal to the minimal wavelength divided by 5, that is, $\lambda/5 = c_0/f_{\text{max}}/5$, where c_0 is the speed of sound.


▼ Element Size Parameters		
Maximum element size:		
343[m/s]/1500[Hz]/5		
Minimum element size:		
16.2	mm	
Maximum element growth rate:		
1.5		
Curvature factor:		
0.6		
Resolution of narrow regions:		
0.5		



Swept I

- On the Mesh toolbar click Swept
- 2 On the Mesh toolbar, click Build Mesh
 . The mesher automatically detects source and destination boundaries for the swept mesh.

3 Click the Zoom Extents button in the Graphics toolbar.




Study I

Step 1: Frequency Domain

- In the Model Builder expand the Study 1 node then click Step 1: Frequency Domain \(\)\(\)\(\)\(\).
- 2 Go to the Settings window for Frequency Domain. Under Study Settings in the Frequencies text field, enter range (50, 25, 1500).

- 3 Locate the Physics and Variables Selection section. Select the Modify physics tree and variables for study step check box.
- 4 In the tree, under Component 1>Pressure Acoustics, Frequency Domain, click Poroacoustics 1.
- 5 Click the Disable button under the table.
- 6 On the Settings window or Home toolbar click Compute = .



Results

The first default plot shows the pressure distribution on the walls of the muffler at the highest frequency, 1500 Hz. To get a better view of the standing wave pattern, you can plot the norm of the pressure instead of the real part of the pressure.


Acoustic Pressure (acpr)



2 Go to the Settings window for Surface. In the upper-right corner of the Expression section, click Replace Expression


▼ .

3 From the menu, search for acpr.absp and double-click to add it to the Expression text field (or enter acpr.absp in the field).




The default plots use a symmetric color range to better visualize the pressure and the wave nature of acoustics. Switch this off when looking at the absolute pressure.

- 4 Locate the Coloring and Style section. Clear the Symmetrize color range check box.



The pattern is very different at different frequencies. See for example what happens at 1250 Hz.

- In the Model Builder under Results, click Acoustic Pressure (acpr)
- **2** Go to the Settings window for 3D Plot Group. Under Data from the Parameter value (freq) list, choose 1250.0.
- 3 On the 3D Plot Group toolbar click the Plot button .




At 1250 Hz, the absolute value of the pressure does not vary much with the x-coordinate. The reason is that this is just higher than the cutoff frequency for the first symmetric propagating mode, which is excited by the incoming wave. For a separate analysis of the propagating modes in the chamber, see the description for the Eigenmodes in a Muffler model.

The two other default plot groups show the sound pressure level on the wall surface and the pressure inside the muffler as isosurfaces.

Acoustic Pressure, Isosurfaces (acpr)

In the Model Builder under Acoustic Pressure, Isosurfaces (acpr), click the Isosurface node it to display the plot in the next figure.



freq(59)=1500 Hz Isosurface: Total acoustic pressure field (Pa)

Proceed to plot the transmission loss of the muffler system. Use the Octave Band Plot as it allow to plot any transfer function both as band plots and as continuous curves (sweeps).

ID Plot Group 4

- I On the Home toolbar, click Add Plot Group and choose 1D Plot Group \sim .
- 2 In the Settings window for 1D Plot Group, type Transmission Loss, Continuous in the Label text field.

Transmission Loss, Continuous

- On the Transmission Loss, Continuous toolbar, click Octave Band Plot
- **2** In the Settings window for Octave Band Plot, locate the Selection section.
- 3 From the Geometric entity level list, choose Global.

 Start by locating and inspecting the postprocessing variables available for the port boundary conditions. Add the variable for the power of the incident mode at Port 1. Then modify the expression manually to get the ratio to the power of the outgoing wave at Port 2. This will give the transmission loss.

- 4 In the upper-right corner of the y-axis data section, click Replace Expression

 ↓ ▼ . From the menu, choose Component 1>

 Pressure Acoustics, Frequency Domain>Ports>Port 1>
 acpr.port1.P_in Power of incident mode W.
- 5 Locate the y-Axis Data section. In the Expression text field, type acpr.port1.P_in/acpr.port2.P_o ut.
- **6** From the Expression type list, choose Transfer function.
- 7 Locate the Plot section. From the Style list, choose Continuous.
- 8 Locate the Legends section. Select the Show legends check box.
- **9** From the Legends list, choose Manual.
- **10** In the table, enter the following settings:



II On the Transmission Loss, Continuous toolbar, click Plot <a> □

The plot should be a reproduction of the blue curve in Figure 9.



Model Wizard

Proceed to solve the model including a layer of absorptive glass wool on the muffler line. Continue working from where you left off with the model developed thus far and add a second study to keep your existing results intact. The first task is to add a second study to keep the existing results intact.


I On the Home toolbar click Add Study [∞].

2 Go to the Add Study window. Under Studies click Frequency Domain ∭. Click Add Study ♣. A Study 2 node is added to the Model Builder.

3 On the Home toolbar, click Add Study to close the Add Study window.

Study 2

- In the Model Builder click Study 2
- 2 In the Settings window for Study under the Study Settings section, click to clear the Generate default plots check box.



Step 1: Frequency Domain

- Under Study 2 click Step 1: Frequency Domain \(\) \(\).
- **2** In the Settings window for Frequency Domain locate the Study Settings section.
- 3 In the Frequencies text field enter range (50, 25, 1500).




4 On the Settings window or Home toolbar click Compute = .

Results


You chose not to have new default plots generated. Once the solution process is finished you can use the existing plot groups and just switch the data set to see how the damping material affects the solution.

Acoustic Pressure, Isosurfaces (acpr)


In the Model Builder under Results, click the Acoustic Pressure, Isosurfaces (acpr) node.



2 In the Settings window for 3D Plot Group under Data, from the Data set list choose Study2/Solution 2.



3 On the Settings window click the Plot button **a** .



At 1500 Hz, the pressure in the chamber is much lower than before.

Proceed to study how the transmission loss has changed with the addition of the lining. Duplicate the first plot and select the new data set, first do a bit of formatting.


Transmission Loss, Continuous

- In the Model Builder window, under Results click Transmission Loss, Continuous.
- 2 In the Settings window for 1D Plot Group, click to expand the Title section.
- **3** From the Title type list, choose Manual.
- 4 In the Title text area, type Transmission Loss, Continuous.
- **5** Locate the Plot Settings section. Select the y-axis label check box.
- **6** In the associated text field, type Power, incoming wave (dB, rel. outgoing wave).
- 7 Click to expand the Legend section. From the Position list, choose Upper left.
- 8 In the Model Builder window, under Results>Transmission Loss, Continuous right-click Octave Band Plot 1 and choose Duplicate.
- 9 In the Settings window for Octave Band Plot, locate the Data section.
- 10 From the Data set list, choose Study 2/Solution 2 (sol2).

II Click to expand the Legends section. In the table, enter the following settings:

LEGENDS	
Absorptive	liner

2 On the Transmission Loss, Continuous toolbar, click Plot .



The plot should look like that in Figure 9 top.

Duplicate the Transmission Loss plot and change the format to 1/3 octave bands.


Transmission Loss, Continuous I

- In the Model Builder window, right-click Transmission Loss, Continuous and choose Duplicate.
- 2 In the Settings window for 1D Plot Group, type Transmission Loss, 1/3 Octave Bands in the Label text field.
- 3 Locate the Title section. In the Title text area, type Transmission Loss, 1/3 Octave Bands.


Transmission Loss, 1/3 Octave Bands

- In the Model Builder window, expand the Results>Transmission Loss, 1/3 Octave Bands node, then click Octave Band Plot 1.
- 2 In the Settings window for Octave Band Plot, locate the Plot section.

3 From the Style list, choose 1/3 octave bands.



- 4 In the Model Builder window, under Results>Transmission Loss, 1/3 Octave Bands click Octave Band Plot 2.
- 5 In the Settings window for Octave Band Plot, locate the Plot section.
- **6** From the Style list, choose 1/3 octave bands.
- 7 Click to expand the Coloring and style section. Locate the Coloring and Style section. From the Type list, choose Curve.
- 8 In the Width text field, type 2.




The plot should look like that in Figure 9 bottom.

Now, create a plot that represents the intensity flux through the muffler system. Use streamlines that follow the intensity vector (flux of energy through the muffler). You can change between solutions and frequencies to study and visualize the muffler's sound-absorbing properties.


3D Plot Group 5

Intensity

- On the Results toolbar click 3D Plot Group
- 2 In the Settings window for 3D Plot Group 5, enter Intensity in the Label text field.
- 3 On the Intensity toolbar click Streamline ≥.
- 5 From the menu, search for Intensity (RMS) or acpr.Ix,acpr.Iy,acpr.Iz. Double-click to add it to the Expression text field (or enter acpr.Ix,acpr.Iy,acpr.Iz in the field).




- 6 Under Selection select Boundary 1 only to add it to the selection list.
- 7 Under Coloring and Style:
 - From the Line type list choose Tube.
 - In the Tube radius expression text field enter 2.



8 In the Model Builder under Intensity, right-click Streamline 1 ≥ and choose Color Expression . □

- 9 In the Settings window for Color Expression enter acpr.I_rms in the Expression text field (replace the default).
- **10** On the Settings window click Plot **◎** .



This should reproduce Figure 10.

As a final step, pick one of the plots to use as a model thumbnail.


- In the Model Builder under Results, click Acoustic Pressure, Isosurfaces
- 2 Click the Root node (the first node in the model tree). On the Settings window for Root under Model Thumbnail, click Set Model Thumbnail.

Make adjustments to the image in the Graphics window using the toolbar buttons until the image is one that is suitable to your purposes.

Geometry Sequence linstructions

In the Model Builder under Component 1, click Geometry 1 🔌.

2 Go to the Settings window for Geometry. Under Units from the Length unit list, choose mm.




Work Plane I


- I On the Geometry toolbar click Work Plane \(\bigsim_{\circ} \).
- **2** Go to the Settings window for Work Plane. Under Plane Definition, from the Plane list choose yz-plane.

Rectangle 1

- I Right-click Plane Geometry Å and add a Rectangle

 .
- **2** Go to the Settings window for Rectangle. Under Size in the:
 - Width text field, enter W.
 - Height text field, enter H.
- 3 Locate the Position section. From the Base list, choose Center.






Fillet 1

- On the Work plane toolbar click Fillet .
- 2 On the object r1, select Points 1,2,3,4 only.


Note: There are many ways to select geometric entities. When you know the points to add, such as in this exercise, you can click the Paste Selection button and enter the information in the Selection text field. In this example for the Fillet 1 node, enter 1,2,3, 4 in the Paste Selection window. For more information about selecting geometric entities in the Graphics window, see the *COMSOL Multiphysics Reference Manual*.



3 Go to the Settings window for Fillet. Under Radius in the Radius text field, enter H/2.

Rectangle 2


- **2** Go to the Settings window for Rectangle. Under Size in the:
 - Width text field, enter W-2*D.
 - Height text field, enter H-2*D.
- 3 Locate the Position section. From the Base list, choose Center.



Fillet 2


- On the Work plane toolbar, click Fillet / .
- 2 On the object r2, select Points 1,2,3,4 only.
- 3 Go to the Settings window for Fillet. Under Radius in the Radius text field, enter (H-2*D)/2.
- 4 Click the Build All button 📳 on the Settings window or Home toolbar.

The geometry in the Graphics window and the node sequence under Work Plane 1 should match these figures at this point:



Extrude I

- I On the Work plane toolbar, click Close 🔕.
- 2 On the Geometry toolbar click Extrude .
- **3** Go to the Settings window for Extrude. Under Distances from Plane in the table under Distances (mm), enter L in the column (replace the default).




Cylinder I

On the Geometry toolbar click Cylinder .


- **2** Go to the Settings window for Cylinder. Under Size and Shape in the:
 - Radius text field, enter R io.
 - Height text field, enter L_io.
- 3 Under Position in the x text field, enter -L io.
- 4 Under Axis:
 - From the Axis type list, choose Cartesian.
 - In the x text field, enter 1.
 - In the z text field, enter 0.

Cylinder 2


- On the Geometry toolbar click Cylinder .
- 2 Go to the Settings window for Cylinder. Under Size and Shape in the:
 - Radius text field, enter R_io.
 - Height text field, enter L io.
- **3** Under Position in the x text field, enter L.
- 4 Under Axis:
 - From the Axis type list, choose Cartesian.
 - In the x text field, enter 1.
 - In the z text field, enter 0.
- 5 Click the Build All button on the Home toolbar. Click the Zoom Extents button on the Graphics toolbar.



The node sequence in the Model Builder should match the figure.



The finished geometry is shown in the figure below, the axis dimensions are in mm, as selected, and the system of coordinates is also shown.




Additional Examples from the Application Libraries

The Acoustics Module application library has other tutorials available as well as advanced industrial and verification models. Short explanations and examples are given below for a cross-section of these models. Go to The Application Libraries Window to learn how to access these model files from COMSOL Multiphysics.

Eigenmodes in a Muffler

In this model, the propagating modes in the chamber of an automotive muffler are computed. The geometry is a cross-section of the chamber as described in the Absorptive Muffler example in this guide.


The purpose of the model is to study the shape of the propagating modes and to find the cut-off frequencies. As discussed in the Absorptive Muffler tutorial, some of the modes significantly affect the damping of the muffler at frequencies above the cut-off. In the Eigenmodes in Muffler model, modes with cut-off frequencies up to 1500 Hz are studied.



First fully symmetric propagation mode of the muffler chamber (with no absorbing liner). The plot shows the absolute value of the pressure.

Piezoacoustic Transducer

A piezoelectric transducer can be used either to transform an electric current to an acoustic pressure field or, the opposite, to produce an electric current from an acoustic field. These devices are generally useful for applications that require the generation of sound in air and liquids. Examples of such applications include phased array microphones, ultrasound equipment, inkjet droplet actuators, sonar transducers, and devices for drug discovery, bioimaging, and acousto-biotherapeutics.




Surface and height plot of the pressure distribution created by the piezoactuator at f = 100 kHz.

Loudspeaker Driver in a Vented Enclosure

An important class of acoustic models are transducers, that is, electro-mechanic-acoustic transducers. Transducers are true multiphysics models that often in addition to acoustics necessitate a structural mechanics and an electromagnetic interface is added. One such class are loudspeakers (presented here), another are microphones presented below.

This model of a boxed loudspeaker lets you apply a nominal driving voltage and extract the resulting sound pressure level in the outside room as a function of the frequency. The electromagnetic properties of the driver are supplied from the Loudspeaker Driver model (available with the AC/DC Module). The model uses

the Acoustic-Shell Interaction interface and therefore requires the Structural Mechanics Module.




Iso-pressure contours (in gray scale) and deformation of the speaker cone (colors).

The Brüel & Kjær 4134 Condenser Microphone

Another type of transducer is the microphone. This is a model of the Brüel and Kjær 4134 condenser microphone. The geometry and material parameters are those of the microphone. The modeled sensitivity level is compared to measurements performed on an actual microphone and shows good agreement. The membrane deformation, pressure, velocity, and electric field are also

determined. The model requires the Acoustics Module, the AC/DC Module, and the Structural Mechanics Module.



Deformation of the microphone membrane (diaphragm) at 20 kHz. The geometry is courtesy of Brüel & Kjær.

This concludes this introduction.